



# Enterprise Data Platform (EDP) Tutorial

11.2

February 2026

## DOCUMENT ACCESS

Public

## DISCLAIMER

The contents of this document are under copyright of Critical Manufacturing S.A. It is released on condition that it shall not be copied in whole, in part or otherwise reproduced (whether by photographic, or any other method) and the contents therefore shall not be divulged to any person other than that of the addressee (save to other authorized offices of his organization having need to know such contents, for the purpose for which disclosure is made) without prior written consent of submitting company.

# Enterprise Data Platform (EDP) Tutorial

Estimated time to read: 3 minutes


## Overview

The Enterprise Data Platform (EDP) creates a **central CDM Data Lake** that aggregates data from all MES installations belonging to a customer.

Local sites replicate their operational data into a **shared ClickHouse database**, where the EDP House Keeper processes it into a unified CDM model.

At a high level, the movement of replicated data from each MES installation into the EDP occurs through the sequence below:

1. **Local MES** - Generates Replication Events and sends to the **Local Kafka**.
2. **EDP Connector** - Consumes local replication topics and forwards events to the **EDP API**.
3. **EDP Service** - Receives the payload and publishes it into the **EDP Kafka topics**.
4. **EDP House Keeper** - Consumes the EDP topics to build the per-installation **ODS** and the centralized **CDM**.



## Information Flow

## Local Environment to EDP Connector

Local MES systems publish two types of messages into Kafka replication topics:

- `dp_replication_events`
- `dp_replication_shids` (Service History IDs)
- `dp_shids_ordered` (Ordered Service History IDs)

The **EDP Connector** consumes these topics from Kafka and forwards the messages to the EDP. The connector must be configured following the instructions described on the [EDP Connector Installation Process](#).

## EDP Connector to EDP Service

The EDP exposes a dedicated API endpoint. For each payload received, the service it identifies the source installation:

- Either extracted from message headers added by the connector.
- Or enriched at the host level on arrival.

The validated payload is then ready to be forwarded into the internal EDP data pipeline.

## EDP Service to EDP House Keeper

After processing the incoming request, the EDP Service publishes the data into the EDP Kafka topics:

- `edp_replication_events`
- `edp_replication_shids`
- `edp_shids_ordered`

These topics are then consumed by the EDP House Keeper, which is responsible for:

- Replicating ODS data into per-installation ClickHouse databases.
- Executing the CDM scripts to build the unified Data Lake.
- Enforcing metadata consistency and schema transformation rules.

This ensures that all incoming data is transformed, normalized, and aligned with the EDP's unified CDM structure.

## EDP House Keeper Responsibilities

As previously mentioned, the EDP House Keeper performs three main functions:

### Replicate ODS Data Per Installation

Each installation receives its own **ClickHouse ODS database**. To perform replication correctly, the House Keeper must load all **metadata** associated with that installation. This metadata is stored across a set of **State** and **History** tables, listed below.

#### State Tables

- `dbo_T_EntityType`
- `dbo_T_EntityTypeProperty`
- `dbo_T_SmartTable`
- `dbo_T_SmartTableProperty`

- `dbo_T_SmartTablePrecedenceKey`
- `dbo_T_GenericTable`
- `dbo_T_GenericTableProperty`
- `dbo_T_ScalarType`

## History Tables

- `dbo_T_EntityTypeHst`
- `dbo_T_EntityTypePropertyHst`
- `dbo_T_SmartTableHst`
- `dbo_T_SmartTablePropertyHst`
- `dbo_T_SmartTablePrecedenceKeyHst`
- `dbo_T_GenericTableHst`
- `dbo_T_GenericTablePropertyHst`

These metadata tables are stored inside ClickHouse [ODS](#) and must be correctly transferred from local systems.

## Selection and Execution of CDM Scripts

To build the final CDM Data Lake:

- A set of scripts must exist per [MES](#) version.
- Each script set converts that installation's [ODS](#) structure into the EDP-standard CDM structure.

## Maintaining ISA-95 Structure

All ingested data must contain the mandatory ISA-95 hierarchy:

- Enterprise
- Site
- Facility (Area equivalent)

If ISA-95 information is **missing** in the replicated payload, the EDP does not inject default values automatically. Instead, this information is defined through the **Data Silo** entity, which customers must configure for each [MES](#) installation. The Data Silo provides the authoritative defaults for these properties and ensures that all incoming data is grouped and interpreted correctly within the Enterprise Data Platform. To configure the Data Silo entity, follow the steps described in the [EDP Connector Installation Process](#).



# Legal Information

## **Disclaimer**

The information contained in this document represents the current view of Critical Manufacturing on the issues discussed as of the date of publication. Because Critical Manufacturing must respond to changing market conditions, it should not be interpreted to be a commitment on the part of Critical Manufacturing, and Critical Manufacturing cannot guarantee the accuracy of any information presented after the date of publication. This document is for informational purposes only.

Critical Manufacturing makes no warranties, express, implied or statutory, as to the information herein contained.

## **Confidentiality Notice**

All materials and information included herein are being provided by Critical Manufacturing to its Customer solely for Customer internal use for its business purposes. Critical Manufacturing retains all rights, titles, interests in and copyrights to the materials and information herein. The materials and information contained herein constitute confidential information of Critical Manufacturing and the Customer must not disclose or transfer by any means any of these materials or information, whether total or partial, to any third party without the prior explicit consent by Critical Manufacturing.

## **Copyright Information**

All title and copyrights in and to the Software (including but not limited to any source code, binaries, designs, specifications, models, documents, layouts, images, photographs, animations, video, audio, music, text incorporated into the Software), the accompanying printed materials, and any copies of the Software, and any trademarks or service marks of Critical Manufacturing are owned by Critical Manufacturing unless explicitly stated otherwise. All title and intellectual property rights in and to the content that may be accessed through use of the Software is the property of the respective content owner and is protected by applicable copyright or other intellectual property laws and treaties.

## **Trademark Information**

Critical Manufacturing is a registered trademark of Critical Manufacturing.

All other trademarks are property of their respective owners.